

#### PUBLIC 2022-05-04

# **Configuration Guide (CRP)**



## Content

1	Overview
2	Role Concept and Authorization
3	Maintenance of Icon Table for Object Filter 5
4	Jump to Other Transactions from the Capacity Detail View
5	Maintenance of Delivery Restrictions for Sales Order View
6	Availability Check Sales Order View
7	Network Check Sales Order View
8	Maintenance of Available Equipment Capacity
9	Maintenance of Equipment Lifetime
10	Set Chart Templates as User Parameters 12

### **1** Overview

This configuration guide documents the configuration settings for the **Consulting Solution CRP**. The individual areas refer to the user documentation in which the respective scenario is described in detail. Therefore, you should also refer to the user documentation for a complete picture of the functions.

### 2 Role Concept and Authorization

Authorizations can be used to control which of the available roles can be displayed and used. You use transaction /SAPLOM/CRP CAUT to define whether the authorization check is active generally.

The authorization check can be activated with an 'X' in the *Switch* field.

Change View "Sw	itch for er	nabling	authorization checks in CRP Monitor":
😚 New Entries 🗈 🗟 🖙 📑	86		
Switch for enabling authorizat	tion checks in CRI	P Mo	
Description	Switch		
AUTHORIZATION			
		*	

Activation of Authorization Check

In this case, users are only offered roles on the **CRP** selection screen for which they have the corresponding authorization.

The authorization is controlled by the authorization object /SAPLOM/C1. The following characteristics are checked:

- CRP\_ALL All roles
- CRP\_BACKC Backlog view
- CRP\_CAPPC Capacity planning table view
- CRP\_CAPUC Capacity evaluation/tabular capacity planning table view
- CRP\_CAPUD Capacity evaluation/tabular planning table (cannot be changed) view
- CRP\_EXECC Execution view
- CRP\_EXECD Execution view (cannot be changed)
- CRP\_EXECDC Execution view (cannot be changed, confirmations only)

When you use the authorization check, the customer must use the authorization object /SAPLOM/C1 in the role concept.

#### 3 Maintenance of Icon Table for Object Filter

In this Customizing activity, you can specify which icons are to be displayed for the object filter on the Capacity Evaluation/Tabular Planning Table tab. You use transaction /SAPLOM/CRP\_SCUST to access the maintenance area.

Cockpit - ICON Maintenance		
Field Name	+	+ [
ABKRS		
ABRUE		
ANGEB		
APRIO		
ARBEH	æ	Æ
ARBEI		
ARBPL	*	*
ARBPLTEXT	*	*
ARUZE	æ	Æ
ASVRG		
AUART	♦	�
AUFFX	€	€
AUFNR	€	<u>କ୍</u> ତୁ କ୍ତୁ କୁ
AUFTR	€.	€
AUTYP		
AWTXT	1	4
AWVST	4	* * ©
BEARZ	5	5
BEAZE	<b>A</b>	1

Icon Maintenance

#### 4 Jump to Other Transactions from the Capacity Detail View

From the capacity detail view (*Capacity Evaluation/Tabular Planning Table* tab), you can navigate to other transactions.

You can use the maintainable database table /SAPLOM/CRP\_ICON to control the target transaction for branching. This table includes columns for the field name (FIELDNAME) and transaction code (TCODE). You can also adjust the icons in the table. These icons are used to create the two tree structures on the left of the screen and are dependent on the field name.

To maintain the table, enter a transaction code to which you want to branch for a specific field that exists in the pegged requirement table.

P Cockpit - ICON Maintenance		
Field Name	Transaction Code	
ABKRS		
ABRUE	XX00	
ANGEB	S	
APRIO	XX00	
ARBEH		
ARBEI		
ARBPL	CR02	
ARBPLTEXT	CR02	
ARUZE	XX00	
ASVRG		
AUART	XX00	
AUFFX	MD12	
AUFNR	xx00	
AUFTR	XX00	
AUTYP	XX00	
AWTXT		
AWVST		
BEARZ	XX00	
BEAZE	XX00	
BEDARF		
BED_EINH		
BUKRS		

#### **Transaction Calls**

If you enter a value of "XXOO", this means that the system performs a check of the order type for the corresponding field. Depending on the order type and the order number, the system then branches to the transactionsco02/03, MD12/13, IW32/IW33, and so on. For this function to work correctly, a corresponding value must exist in the field <AUTYP> in the table row of the pegged requirement.

For each jump to a transaction, the parameter ID values must be set for all columns, if these values are available. For example, if you call a transaction that has <Material> and <Plant> as the initial fields, it can be assumed that the navigation works by skipping the first screen. This is in part because of the <Material> and <Plant> fields that exist in the pegged requirement table and also because of the automatic setting of parameter IDs for all columns.

#### 5 Maintenance of Delivery Restrictions for Sales Order View

You can use transaction / SAPLOM/ XSR\_SUPRES to maintain delivery restrictions for the vendor check on the sales order view.

88	B.									
aintain	Supplier Restri	ictions								
Pint	Product grou	p Prod.grp description	Vendor	Name	from	to	P. max. Quantity	BUh	yellow (%)	red (%)
1000	DDP-001		1000	C.E.B. BERLIN	18.2020	18.2020	W 10.000	PC	0	0
1000	DDP-001		1000	C.E.B. BERLIN	19.2020	19.2020	W 12.000	PC	0	0
1000	P-100	Pump PRECISION 100	1000	C.E.B. BERLIN	01.2000	12.2014	M 30	PC	85	100
	P-100	Pump PRECISION 100	1000	C.E.B. BERLIN	01.2015	01.2029	N 35	PC	85	100

Maintenance of Vendor Restrictions

Maintenance is always performed at the product group level per plant and vendor for a specific time period. The period indicator determines the bucket size to which the specified maximum quantity relates. Possible bucket sizes are weeks or months. If you specify a period indicator for a key entry, this period indicator applies for all further entries with the same key. If you make entries with overlapping validities, the system adjusts the existing entries and informs you of the adjustment.

### 6 Availability Check Sales Order View

You can use table  $/SAPLOM/CRPJ_SPR$  to define the conditions for the traffic light colors during the availability check of the sales order view.

Displa	iy Vi	ew "CR	P - selectio	on profile for prod. orders
	<b>A</b>			
CRP - sele	ection p	rofile for pro	d. orders availabil	ity check
PInt	Туре	SelProf	Avai	
100	PS04		040	*

Availability Check Sales Order View

You can define a traffic light color for each order type, plant, and status selection profile. The check is based on the status conditions in the status selection profile (you define status selection profiles using transaction BS42). This enables you to define any status conditions for the availability check in principle.

### 7 Network Check Sales Order View

In table /SAPLOM/CRPJ\_SPR the network check can also be configured based on a status selection profile. However, an additional date check is implemented here, which checks whether the relevant network end date has already been reached or exceeded. If this is not the case, the system does not execute the network check in accordance with the table /SAPLOM/CRPJ\_SPR and displays a green traffic light directly.

#### 8 Maintenance of Available Equipment Capacity

You use transaction SM30 (extended table maintenance) to maintain the available capacity of an item of equipment per period (day/week/month) in table /SAPLOM/X\_EQ\_CAP. Depending on the period selected (day/week/month), the system displays the corresponding equipment availability ("Availability" column in the table SAPLOM/X\_EQ\_CAP) for each period line in the "Available Capacity" column of the *Equipment Load* view.

hange View "	Available qua	ntity of equipment": Overview
New Entries 🚺 🗟 🗳		
vailable quantity of equ	pment	
Equipment	Pint +	Availability (Hours)
MK-EQUIP	1000 W Wee}	- 25,000
MK-EQUIP3	1000 W Wee}	<b>30,000</b>
PRT5	1000 D Day	<b>4</b> ,000
PRT5	1000 M Mont	h • 100,000
PRT5	1000 W Wee}	- 25,000

Maintenance of Equipment Availability

### 9 Maintenance of Equipment Lifetime

The total capacity (in the unit of measure of the material produced) is maintained for each piece of equipment in the table /SAPLOM/CRP\_AEQM.

hange View "	CRP - Equipments n	naximum production quantity": Overvi
New Entries 🚯 🗟 🖬	0 B B B	
RP - Equipments maxin	num production quantity	
Equipment	EQ.Max.Capacity	
MK-EQUIP	2.000,000	
MK-EQUIP3	5.000,000	- ·
DDTE	2 110 000	

Maintenance of Maximum Capacity of Equipment in Unit of Measure

### **10** Set Chart Templates as User Parameters

A saved chart template can be set as the default setting for one or more users. To enable this, the parameter / SAPLOM/X\_CHART is maintained in the user master record with a specific combination of the namespace, sequence number, and the name of the template. The compound parameter is created from the fixed namespace '/SAPLOM/CRP' + counter + template name in each case. You can view the counter of a stored template by choosing the *Show Chart* button.

Maintain User P	rofile					
Ressword						
User	D064891					
Last Changed On	D043274	15.10.2020	07:58:58	Status	Saved	
Address Defaults	Parameters					
Parameter ID	Parame	ter value	Short Descriptio	n		<b></b>
/SAPLOM/X_CHAR		M/CRP18GRAFIK123	-			
8AP	S		FI-CA: Applicatio	on in Contract A	ccounting	*
APPLDOM			Application Dom	ain		
BICUG			User Group for E	Batch Informatio	on Cockpit	
			'X' = Automatically Execute Selection at Start			
BIC_AUTOSEL			'X' = Automatica	Ily Execute Sele	ection at Start	
BIC_AUTOSEL BIC_DETAIL_IN_U	WINDOW		'X' = Automatica 'X' = Detail Fund			
_	WINDOW MSCX		'X' = Detail Fund	tion in Separate		

Chart Template as User Parameter

#### **Important Disclaimers and Legal Information**

#### **Hyperlinks**

Some links are classified by an icon and/or a mouseover text. These links provide additional information. About the icons:

- Links with the icon P<sup>2</sup>: You are entering a Web site that is not hosted by SAP. By using such links, you agree (unless expressly stated otherwise in your agreements with SAP) to this:
  - The content of the linked-to site is not SAP documentation. You may not infer any product claims against SAP based on this information.
  - SAP does not agree or disagree with the content on the linked-to site, nor does SAP warrant the availability and correctness. SAP shall not be liable for any damages caused by the use of such content unless damages have been caused by SAP's gross negligence or willful misconduct.
- Links with the icon 2: You are leaving the documentation for that particular SAP product or service and are entering a SAP-hosted Web site. By using such links, you agree that (unless expressly stated otherwise in your agreements with SAP) you may not infer any product claims against SAP based on this information.

#### Videos Hosted on External Platforms

Some videos may point to third-party video hosting platforms. SAP cannot guarantee the future availability of videos stored on these platforms. Furthermore, any advertisements or other content hosted on these platforms (for example, suggested videos or by navigating to other videos hosted on the same site), are not within the control or responsibility of SAP.

#### **Beta and Other Experimental Features**

Experimental features are not part of the officially delivered scope that SAP guarantees for future releases. This means that experimental features may be changed by SAP at any time for any reason without notice. Experimental features are not for productive use. You may not demonstrate, test, examine, evaluate or otherwise use the experimental features in a live operating environment or with data that has not been sufficiently backed up. The purpose of experimental features is to get feedback early on, allowing customers and partners to influence the future product accordingly. By providing your feedback (e.g. in the SAP Community), you accept that intellectual property rights of the contributions or derivative works shall remain the exclusive property of SAP.

#### **Example Code**

Any software coding and/or code snippets are examples. They are not for productive use. The example code is only intended to better explain and visualize the syntax and phrasing rules. SAP does not warrant the correctness and completeness of the example code. SAP shall not be liable for errors or damages caused by the use of example code unless damages have been caused by SAP's gross negligence or willful misconduct.

#### **Bias-Free Language**

SAP supports a culture of diversity and inclusion. Whenever possible, we use unbiased language in our documentation to refer to people of all cultures, ethnicities, genders, and abilities.

© 2022 SAP SE or an SAP affiliate company. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company. The information contained herein may be changed without prior notice.

Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies.

Please see https://www.sap.com/about/legal/trademark.html for additional trademark information and notices.

