



# **Subprograms: Arguments**

## **ICS312 Machine-Level and Systems Programming**

Henri Casanova ([henric@hawaii.edu](mailto:henric@hawaii.edu))

# Activation Records

- The stack is useful to store and retrieve return addresses, transparently managed via the CALL and RET instructions
- But it's much more useful than this
- In general, when calling a function, one puts all kinds of useful information on the stack
- When the function returns, this information is popped off the stack and the function's caller can safely resume execution
- The set of "useful information" is typically called an **activation record** (or a "**stack frame**")
- One very important component of an activation record is the **parameters** passed to the function
- Another is the **return address**, as we've already seen



# Subprogram Conventions

- When writing assembly, you could do whatever you want
- For instance, you could devise a clever scheme that reuses register values in creative ways instead of the stack
- Such solutions are typically error prone, making the code difficult to debug/extend/maintain, but can enhance performance
- Typically, one uses a consistent **calling convention**, so that there is a generic way to call a subprogram
- Of course compilers use calling conventions
  - The compiler, when generating assembly code, follows a standard process to generate assembly for function calls and returns
- Some languages specify which calling convention should be used
- **What we describe in all that follows is (mostly) the convention used by the C language**
  - i.e., C compilers use this convention when generating assembly code from C code
  - we'll also use this convention when writing assembly by hand




# A Simple Activation Record

- To call a function you have to follow these steps:
  - Push the parameters onto the stack
  - Execute the CALL instruction, which pushes the return address onto the stack
- Warning: In the C calling convention parameters are pushed onto the stack **in reverse order!**
  - Say the function is  $f(a,b,c)$
  - $c$  is pushed onto the stack first
  - $b$  is pushed onto the stack second
  - $a$  is pushed onto the stack third
  
  - Makes sense: a pop should get the first parameter


# A Simple Activation Record

- Say you want to **call** a function with two 32-bit parameters
  - If parameters are < 32 bits, they need to be converted to 32-bit values, at least in this course
- After the call, the stack looks like this:



# A Simple Activation Record

- Say you want to **call** a function with two 32-bit parameters
  - If parameters are < 32 bits, they need to be converted to 32-bit values, at least in this course
- After the call, the stack looks like this:





# Using the Parameters

- Inside the code of the subprogram, parameters can be accessed via indirection from the stack pointer
- In our previous example:
  - `mov eax, [ESP + 4]` ; put 1st parameter into eax
  - `mov ebx, [ESP + 8]` ; put 2nd parameter into ebx
- Typically the subprogram does not pop the parameters off the stack before using them
  - It would be annoying to have to pop the return address first, and then push it back
  - It's convenient to have the parameters always stored in memory as opposed to being careful to constantly preserve them in registers
    - They may be copied into registers for performance reasons
    - But we can always get their original values from the stack


# ESP and EBP

- There is one problem with referencing parameters using ESP, as in [ESP+8]
- If the subprogram uses the stack for something else, ESP will be modified!
  - So at some point in the program, the 2nd parameter should be accessed as [ESP+8]
  - And at some other point, it may be accessed as [ESP+12], [ESP+16], etc., depending on how the stack grows
- So the convention is to use the **EBP** register to save the value of ESP as soon as the subprogram starts
- Afterwards, the 2nd parameter is **always** accessed as [EBP+8] and the 1st parameter is **always** accessed as [EBP+4]




# ESP and EBP


- Stack as it is when the subprogram begins



- EBP = ESP




- Further use of the stack



Parameters still referred to as EBP+4 and EBP+8

# ESP and EBP

- So far so good, but the **caller** may have been using EBP!
  - Typically to access its own parameters
- So the convention is to first **save the value of EBP** onto the stack and then set **EBP = ESP**, as soon as the program starts
- So, the stack right before the subprogram truly begins is:



- Parameter accesses:
  - 1st parameter: [EBP+8]
  - 2nd parameter: [EBP+12]

- At the end of the subprogram, the value of EBP is popped and restored with a simple POP instruction

# Subprogram Skeleton

func:

```
push    ebp        ; save original EBP
```

```
mov     ebp, esp   ; set EBP = ESP
```

```
...      ; subprogram code
```

```
pop     ebp        ; restore original EBP
```

```
ret     ; returns
```

# Returning from a Subprogram

- After the subprogram returns, one must “clean up” the stack
- The stack has on it:
  - The old EBP value
  - The return address
  - The parameters
- The old EBP value must be popped in the subprogram (at the end)
- The return address is removed by the RET instruction
  - You don't see the POP, but it's there
- **So the only thing that must be removed from the stack are the parameters**
- The C convention specifies that the **caller** code must do this
  - Other languages specify that the callee must do it
- In fact, it is well known that it's a little bit more efficient to have the subprogram (i.e., the callee) do it!
- So one may wonder why C opts for the slower approach
- Turns out, it's all because of *varargs*

# Variable Number of Arguments

- C allows or the declaration of functions with variable number of arguments
- A well-known example: `printf()`
  - `printf("%d", 2);`
  - `printf("%d %d", 2, 3);`
  - `printf("%s %d %c %f", "foo", 1, 'f', 3.14);`
- So sometimes there will be 1 argument to remove from the stack, sometimes 2, sometimes 3, etc.
- Having the subprogram (in this case `printf`) remove the arguments from the stack requires some complexity
  - e.g., pass an extra (shadow) parameter that specifies how many arguments should be removed
- Instead, the convention is that the caller removes the arguments, because it always knows how many there are
  - e.g., it's easy for a compiler to generate code that does this

# Variable of Arguments in C

- Just in case you are curious, here is an example of a C program with a vararg function

```
#include <stdarg.h>
#include <stdio.h>

int func(int first, ...) {
    va_list args;
    va_start(args, first);
    printf("arg #1 = %d\n", first);
    printf("arg #2 = %d\n", va_arg(args, int));
    printf("arg #2 = %s\n", va_arg(args, char*));
    va_end(args);
}
```

```
int main() {
    func(2, (void*)3, (void*)"foo");
}
```

Vararg functions are a bit dangerous. If you call `va_arg()` more times than there are arguments on the stack, you'll just get bogus values!

# Example: Calling a Subprogram

Caller:

```
push        dword 2        ; second parameter
push        dword 1        ; first parameter
call        func           ; call the function
add         esp, 8         ; pop the two arguments
```

- Note that to pop the two arguments we merely add 8 to the stack pointer ESP
  - Since we do not care to get the values of the arguments at this point, it's quicker than to call pop twice!
  - For the case with one argument, calling pop may be better
- The two arguments stay there in memory but will be overwritten next time a function is called or next time the stack is used
  - We don't zero out "old" value, we just lazily overwrite them later (and besides, what would "zero out" mean?)

# Return Values?

- Often, one wants a subprogram to return a value
  - e.g., a function that computes some number
- There are several ways to do this
- One way is to pass as a parameter the address of a zone of memory in which some result should be written
  - As in: `void foo(int *x);`                      `foo(&a);`
- This is not a *true* return value
  - As in: `int foo();`
- **The C convention is that the return value is always stored in EAX when the function returns**
  - It's the responsibility of the caller to save the EAX value before the call (if needed) and to restore it later



# Recall the NASM Skeleton

; include directives

segment .data

; DX directives

segment .bss

; RESX directives

segment .text

global asm\_main

asm\_main:

enter 0,0

pusha

; Your program here

popa

mov eax, 0

leave

ret

Returns value 0!



# Recall the NASM Skeleton

`; include directives`

`segment .data`

`; DX directives`

`segment .bss`

`; RESX directives`

`segment .text`

`global asm_main`

`asm_main:`

`enter 0,0`

`pusha`

`; Your program here`

`popa`

`mov eax, 0`

`leave`

`ret`

The last two remaining things that we haven't explained yet (but soon)

# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    push   [ebp+8]
```

```
    push   8
```

```
    call   reference
```

```
    add    esp, 8
```

```
    add    eax, 10
```

```
    pop    ebp
```

```
    ret
```

```
reference:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    mov    eax, [ebp+12]
```

```
    add    eax, [ebp+8]
```

```
    mov    eax, [eax]
```

```
    pop    ebp
```

```
    ret
```

ESP →

XXXX

# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
    push    ebp
```

```
    mov     ebp, esp
```

```
    push   [ebp+8]
```

```
    push   8
```

```
    call   reference
```

```
    add    esp, 8
```

```
    add    eax, 10
```

```
    pop    ebp
```

```
    ret
```

```
reference:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    mov    eax, [ebp+12]
```


```
    add    eax, [ebp+8]
```

```
    mov    eax, [eax]
```

```
    pop    ebp
```

```
    ret
```

ESP →



# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
push   ebp
```

```
mov    ebp, esp
```

```
push   [ebp+8]
```

```
push   8
```

```
call   reference
```

```
add    esp, 8
```

```
add    eax, 10
```

```
pop    ebp
```

```
ret
```

```
reference:
```

```
push   ebp
```

```
mov    ebp, esp
```


```
mov    eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov    eax, [eax]
```

```
pop    ebp
```

```
ret
```



# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    push  [ebp+8]
```

```
    push  8
```

```
    call  reference
```

```
    add   esp, 8
```

```
    add   eax, 10
```

```
    pop   ebp
```

```
    ret
```

```
reference:
```

```
    push  ebp
```

```
    mov   ebp, esp
```


```
    mov   eax, [ebp+12]
```

```
    add   eax, [ebp+8]
```

```
    mov   eax, [eax]
```

```
    pop   ebp
```

```
    ret
```



# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
push    ebp
```

```
mov     ebp, esp
```

```
push    [ebp+8]
```

```
push    8
```

```
call    reference
```

```
add     esp, 8
```

```
add     eax, 10
```

```
pop     ebp
```

```
ret
```

```
reference:
```

```
push    ebp
```

```
mov     ebp, esp
```


```
mov     eax, [ebp+12]
```

```
add     eax, [ebp+8]
```

```
mov     eax, [eax]
```

```
pop     ebp
```

```
ret
```



# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
    push    ebp
```

```
    mov     ebp, esp
```

```
    push   [ebp+8]
```

```
    push   8
```

```
    call   reference
```

```
    add    esp, 8
```

```
    add    eax, 10
```

```
    pop    ebp
```

```
    ret
```

```
reference:
```

```
    push    ebp
```

```
    mov     ebp, esp
```


```
    mov     eax, [ebp+12]
```

```
    add     eax, [ebp+8]
```

```
    mov     eax, [eax]
```

```
    pop    ebp
```

```
    ret
```





# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
push   ebp
```

```
mov    ebp, esp
```

```
push   [ebp+8]
```

```
push  8
```

```
call   reference
```

```
add    esp, 8
```

```
add    eax, 10
```

```
pop    ebp
```

```
ret
```

```
reference:
```

```
push   ebp
```

```
mov    ebp, esp
```


```
mov    eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov    eax, [eax]
```

```
pop    ebp
```

```
ret
```



# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
push   ebp
```

```
mov    ebp, esp
```

```
push   [ebp+8]
```

```
push   8
```

```
call  reference
```

```
add    esp, 8
```

```
add    eax, 10
```

```
pop    ebp
```

```
ret
```

```
reference:
```

```
push   ebp
```

```
mov    ebp, esp
```


```
mov    eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov    eax, [eax]
```

```
pop    ebp
```

```
ret
```



# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
push   ebp
```

```
mov    ebp, esp
```

```
push   [ebp+8]
```

```
push   8
```

```
call   reference
```

```
add    esp, 8
```

```
add    eax, 10
```

```
pop    ebp
```

```
ret
```

```
reference:
```

```
push   ebp
```

```
mov    ebp, esp
```


```
mov    eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov    eax, [eax]
```

```
pop    ebp
```

```
ret
```



# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
push   ebp
```

```
mov    ebp, esp
```

```
push   [ebp+8]
```

```
push   8
```

```
call   reference
```

```
add    esp, 8
```

```
add    eax, 10
```

```
pop    ebp
```

```
ret
```

```
reference:
```

```
push   ebp
```

```
mov    ebp, esp
```


```
mov    eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov    eax, [eax]
```

```
pop    ebp
```

```
ret
```



# A Full Example

```
L    dd 42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
push    ebp
```

```
mov     ebp, esp
```

```
push    [ebp+8]
```

```
push    8
```

```
call    reference
```

```
add     esp, 8
```

```
add     eax, 10
```

```
pop     ebp
```

```
ret
```

```
reference:
```

```
push    ebp
```

```
mov     ebp, esp
```


```
mov     eax, [ebp+12]
```

```
add     eax, [ebp+8]
```

```
mov     eax, [eax]
```

```
pop     ebp
```

```
ret
```



ESP →  
EBP →

EAX = L

# A Full Example

```
L    dd 42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
push    ebp
```

```
mov     ebp, esp
```

```
push    [ebp+8]
```

```
push    8
```

```
call    reference
```

```
add     esp, 8
```

```
add     eax, 10
```

```
pop     ebp
```

```
ret
```

```
reference:
```

```
push    ebp
```

```
mov     ebp, esp
```


```
mov     eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov     eax, [eax]
```

```
pop     ebp
```

```
ret
```



ESP →  
EBP →

**EAX = L + 8**

# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
push    ebp
```

```
mov     ebp, esp
```

```
push    [ebp+8]
```

```
push    8
```

```
call    reference
```

```
add     esp, 8
```

```
add     eax, 10
```

```
pop     ebp
```

```
ret
```

```
reference:
```

```
push    ebp
```

```
mov     ebp, esp
```


```
mov     eax, [ebp+12]
```

```
add     eax, [ebp+8]
```

```
mov     eax, [eax]
```

```
pop     ebp
```

```
ret
```



$EAX = [L + 8] = 44$

# A Full Example

```
L    dd 42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
push    ebp
```

```
mov     ebp, esp
```

```
push    [ebp+8]
```

```
push    8
```

```
call    reference
```

```
add     esp, 8
```

```
add     eax, 10
```

```
pop     ebp
```

```
ret
```

```
reference:
```

```
push    ebp
```

```
mov     ebp, esp
```


```
mov     eax, [ebp+12]
```

```
add     eax, [ebp+8]
```

```
mov     eax, [eax]
```

```
pop     ebp
```

```
ret
```



EAX = 44



# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
push   ebp
```

```
mov    ebp, esp
```

```
push   [ebp+8]
```

```
push   8
```

```
call   reference
```

```
add    esp, 8
```

```
add    eax, 10
```

```
pop    ebp
```

```
ret
```

```
reference:
```

```
push   ebp
```

```
mov    ebp, esp
```


```
mov    eax, [ebp+12]
```

```
add    eax, [ebp+8]
```

```
mov    eax, [eax]
```

```
pop    ebp
```

```
ret
```



EBP →

ESP →

EAX = 44

# A Full Example

```
L    dd 42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
push    ebp
```

```
mov     ebp, esp
```

```
push    [ebp+8]
```

```
push    8
```

```
call    reference
```

```
add     esp, 8
```

```
add     eax, 10
```

```
pop     ebp
```

```
ret
```

```
reference:
```

```
push    ebp
```

```
mov     ebp, esp
```


```
mov     eax, [ebp+12]
```

```
add     eax, [ebp+8]
```

```
mov     eax, [eax]
```

```
pop     ebp
```

```
ret
```



EAX = 44

# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
    push    ebp
```

```
    mov     ebp, esp
```

```
    push    [ebp+8]
```

```
    push    8
```

```
    call    reference
```

```
    add     esp, 8
```

```
    add     eax, 10
```

```
    pop     ebp
```

```
    ret
```

```
reference:
```

```
    push    ebp
```

```
    mov     ebp, esp
```


```
    mov     eax, [ebp+12]
```

```
    add     eax, [ebp+8]
```

```
    mov     eax, [eax]
```

```
    pop     ebp
```

```
    ret
```



EBP →  
ESP →

$EAX = 44 + 10 = 54$

# A Full Example

```
L    dd  42, 43, 44, 45, 56
```

```
...
```

```
push    dword L
```

```
call    func
```

```
add     esp, 4
```

```
call    print_int
```

```
...
```

```
func:
```

```
    push    ebp
```

```
    mov     ebp, esp
```

```
    push    [ebp+8]
```

```
    push    8
```

```
    call    reference
```

```
    add     esp, 8
```

```
    add     eax, 10
```

```
    pop     ebp
```

```
    ret
```

```
reference:
```

```
    push    ebp
```

```
    mov     ebp, esp
```


```
    mov     eax, [ebp+12]
```

```
    add     eax, [ebp+8]
```

```
    mov     eax, [eax]
```

```
    pop     ebp
```

```
    ret
```



EAX = 54

# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
call   func
add    esp, 4
call   print_int
```

```
...
```


```
func:
```

```
    push   ebp
    mov    ebp, esp
    push   [ebp+8]
    push   8
    call   reference
    add    esp, 8
    add    eax, 10
    pop    ebp
    ret
```

```
reference:
```

```
    push   ebp
    mov    ebp, esp
    mov    eax, [ebp+12]
    add    eax, [ebp+8]
    mov    eax, [eax]
    pop    ebp
    ret
```

ESP →



EAX = 54

# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    push   [ebp+8]
```

```
    push   8
```

```
    call   reference
```

```
    add    esp, 8
```

```
    add    eax, 10
```

```
    pop    ebp
```

```
    ret
```

```
reference:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    mov    eax, [ebp+12]
```

```
    add    eax, [ebp+8]
```

```
    mov    eax, [eax]
```

```
    pop    ebp
```

```
    ret
```

ESP →

XXXX

EAX = 54

# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    push  [ebp+8]
```

```
    push  8
```

```
    call  reference
```

```
    add   esp, 8
```

```
    add   eax, 10
```

```
    pop   ebp
```

```
    ret
```

```
reference:
```

```
    push  ebp
```

```
    mov   ebp, esp
```

```
    mov   eax, [ebp+12]
```

```
    add   eax, [ebp+8]
```

```
    mov   eax, [eax]
```

```
    pop   ebp
```

```
    ret
```

ESP →

XXXX

prints "54"



# A Full Example with Subprograms

- The book has a full example in Section 4.5.1
- Let's do another example here
- Say we want to write a program that first reads in a sequence of 10 integers and then prints the number of odd integers
- We will use three functions:
  - `get_integers()`: get the 10 integers from the user
  - `count_odds()`: count the number of odd integers
  - `is_odd()`: determines whether an integer is odd
- We could do this without functions
  - The code would most likely be less readable
    - But faster! (usual tradeoff)
- For now, we're writing the code in the most modular and "clean" fashion
- Let's first look at the easy main program



# Example: Main program

```
%include "asm_io.inc"
```

```
segment .data
```

```
    msg_odd db    "The number of odd numbers is: ",0
```

```
segment .bss
```

```
    integers resd 10 ; space for 10 integers
```

```
segment .text
```

```
    global asm_main
```

```
asm_main:
```

```
    enter    0,0      ; set up
```

```
    pusha                    ; set up
```

```
    popa                    ; clean up
```

```
    mov     eax, 0        ; clean up
```

```
    leave                   ; clean up
```

```
    ret                    ; clean up
```

```
    push    integers      ; we pass integers (address) to get_integers
    push    dword 10      ; we pass the number of integers to get_integers
    call   get_integers   ; call get_integers
    add    esp, 8         ; clean up the stack
    mov    eax, msg_odd   ; store the address of the message to print into eax
    call   print_string   ; print the message
    push    integers      ; we pass integers (address) to count_odds
    push    dword 10      ; we pass the number of integers to count_odds
    call   count_odds     ; call count_odds
    add    esp, 8         ; clean up the stack
    call   print_int      ; print the content of eax as an integer
                                ; (this is what count_odds returned)
    call   print_nl       ; print a new line
```



## **Piecemeal segment declarations**

- The NASM assembler allows for the declaration of multiple `.data`, `.bss`, and `.text` segments
- This makes it possible to declare subprograms in their own region of the `.asm` file, with parts of `.data` and `.bss` segments that are relevant for the subprograms
- Let's look at the `get_integers()` subprogram

# Example: get\_integers

```
; FUNCTION: Get_Integers
; Takes two parameters: an address in memory in which to store integers, and a number of integers to store (>0)
; Destroys values of eax, ebx, and ecx!!
```

```
segment .data
    msg_int    db    "Enter an integer: ",0
```

```
segment .text
```

```
get_integers:
```

```
    push    ebp                ; save the value of EBP of the caller
    mov     ebp, esp          ; update the value of EBP for this subprogram
```

```
    mov     ecx, [ebp + 12]    ; ECX = address at which to store the integers (parameter #2)
    mov     ebx, [ebp + 8]     ; EBX = number of integers to read (parameter #1)
    shl     ebx, 2             ; EBX = EBX * 4 (unsigned)
    add     ebx, ecx           ; EBX = ECX + EBX = address beyond that of the last integer to be stored
```

```
loop1:
```

```
    mov     eax, msg_int      ; EAX = address of the message to print
    call    print_string;    ; print the message
    call    read_int          ; read an integer from the keyboard (which will be stored in EAX)
    mov     [ecx], eax        ; store the integer in memory at the correct address
    add     ecx, 4            ; ECX = ECX + 4
    cmp     ecx, ebx          ; compare ECX, EBX
    jb     loop1              ; if ECX < EBX, jump to loop1 (unsigned)
```

```
    pop     ebp                ; restore the value of EBP
    ret                          ; clean up
```

# Example: count\_odds

```
; FUNCTION: count_odds
; Takes two parameters: an address in memory in which integers are stored, and the number of integers (>0)
; Destroys values of eax, ebx, and edx!! (eax = returned value)
```

```
segment .text
```

```
count_odds:
```

```
    push    ebp                ; save the value of EBP of the caller
    mov     ebp, esp          ; update the value of EBP for this subprogram
```

```
    mov     eax, [ebp + 12]    ; EAX = address at which integers are stored (parameter #2)
    mov     ebx, [ebp + 8]     ; EBX = number of integers (parameter #1)
    shl     ebx, 2            ; EBX = EBX * 4 (unsigned)
    add     ebx, eax          ; EBX = EAX + EBX = address beyond that of the last integer
    sub     ebx, 4            ; EBX = EBX - 4 = address of the last integer
    xor     edx, edx          ; EDX = 0 = number of odd integers
```

```
loop2:
```

```
    push   dword [ebx]        ; store the current integer on the stack
    call   is_odd             ; call is_odd
    add    esp, 4              ; clean up the stack
    add    edx, eax           ; EDX += EAX (EAX = 0 if even, EAX = 1 if odd)
    sub    ebx, 4             ; EBX = EBX - 4
    cmp    ebx, [ebp+12]     ; compare EBX and the address of the first integer
    jnb   loop2              ; if EBX >= [EBP+12] jump to loop2 (unsigned test)
```

```
    mov    eax, edx          ; EAX = EDX (= number of odd integers)
```

```
    pop    ebp              ; restore the value of EBP
    ret                                ; clean up
```

# Example: is\_odd

```
; FUNCTION: is_odd  
; Takes one parameter: an integers (>0)  
; Destroys values of eax and ecx (eax = returned value)
```

```
segment .text
```

```
is_odd:
```

```
    push    ebp                ; save the value of EBP of the caller  
    mov     ebp, esp          ; update the value of EBP for this subprogram  
  
    mov     eax, 0             ; EAX = 0  
    mov     ecx, [ebp+8]      ; EBX = integer (parameter #1)  
    shr     ecx, 1             ; Right logical shift  
    adc     eax, 0             ; EAX = EAX + carry (if even: EAX = 0, if odd: EAX = 1)  
  
    pop     ebp                ; restore the value of EBP  
    ret
```



# Destroyed Registers?

- Note that in the previous program we have added comments specifying which registers are destroyed
- The caller is then responsible for making sure that its registers are not corrupted
- One way to ensure this is to save them somewhere in memory, for instance on the stack
- However, in a program that has many functions it becomes really annoying to constantly have to pay attention to what needs to be saved and what doesn't
- The typical approach is to have the subprogram save what it knows needs to be saved
  - And comment that the caller doesn't need to worry about anything
- Let's look at typical approaches

# Saving Registers in Subprograms

## ■ Just saving EBP

func:

```
push    ebp           ; save original EBP
mov     ebp, esp      ; set EBP = ESP

...           ; subprogram code

mov     eax, ...      ; set return value

pop     ebp           ; restore original EBP
ret                                ; returns
```

# Saving Registers in Subprograms

- Saving, for instance, EBX and ECX, in addition to EBP

func:

```
push     ebp           ; save original EBP
mov      ebp, esp     ; set EBP = ESP
push     ebx           ; save EBX
push     ecx           ; save ECX

...           ; subprogram code

mov      eax, ...     ; set return value

pop      ecx           ; restore ECX
pop      ebx           ; restore EBX
pop      ebp           ; restore ebp
ret
```



# Saving Registers in Subprograms

- Saving “all” registers using PUSHA and POPA

func:

```
push        ebp                ; save original EBP
mov         ebp, esp          ; set EBP = ESP
pusha      ; save all (including new EBP)

...                               ; subprogram code

mov         eax, ...          ; set return value

popa      ; restore all (including new EBP)
pop        ebp                ; restore original ebp
ret                               ; returns
```

# Saving Registers in Subprograms

- Saving “all” registers using PUSHAD and POPAD

func:

```
push        ebp                ; save original EBP
mov         ebp, esp          ; set EBP = ESP
pushad     ; save all (including new EBP)

...                               ; subprogram code

mov         eax, ...          ; set return value

popad     ; restore all (including new EBP)
pop        ebp                ; restore original ebp
ret                               ; returns
```

Overwrites the return value  
that's stored in eax!

# Saving Registers in Subprograms

- Saving “all” registers using PUSHAD and POPAD, a good option

```
.bss:
    returnvalue    resd    1        ; place in memory for the return value
func:
    push          ebp            ; save original EBP
    mov           ebp, esp      ; set EBP = ESP
    pushad        ; save all (including new EBP)

    . . .                    ; subprogram code

    mov           [returnvalue], eax ; save return value in memory

    popad         ; restore all (including new EBP)
    mov           eax, [returnvalue] ; retrieve the saved return value
                                   ; (as done in our skeleton)

    pop           ebp            ; restore original ebp
    ret           ; returns
```



# Recursion

- The subprogram calling conventions we have just described enable recursion
- Let's see this on an example program that computes the sum of the first  $n$  integers
  - Yes, it's  $n(n+1)/2$ , and even if we didn't know that an iterative program would be more efficient, but for the sake of this example let's just write a recursive program to compute it

# Example: Recursive Program

...

**segment .data**

```
msg1      db      'Enter n: ', 0
msg2      db      'The sum is: ', 0
```

**segment .text**

```
... ; declaration of asm_main and setup

mov      eax, msg1      ; eax = address of msg1
call     print_string   ; print msg1
call     read_int       ; get an integer from the keyboard (in EAX)
push    eax             ; put the integer on the stack (parameter #1)
call     recursive_sum  ; call recursive_sum
add     esp, 4          ; remove the parameter from the stack
mov     ebx, eax        ; save the value returned by recursive_sum
mov     eax, msg2       ; eax = address of msg2
call     print_string   ; print msg2
mov     eax, ebx        ; eax = sum
call     print_int      ; print the sum
call     print_nl       ; print a new line

... ; cleanup
```

# Example: recursive\_sum()

```
segment .bss
    value                resd, 1                ; to store the return value temporarily
segment .text
recursive_sum
    push                 ebp                    ; save ebp
    mov                 ebp, esp                ; set EBP = ESP
    pusha                ; save all registers (probably overkill)
    mov                 ebx, [ebp+8]           ; ebx = integer (parameter #1)
    cmp                 ebx, 0                 ; ebx = 0 ?
    jnz                 next                  ; if (ebx != 0) go to next
    xor                 ecx, ecx                ; ECX = 0
    jmp                 end                    ; Jump to end
next:
    mov                 ecx, ebx                ; ECX = EBX
    dec                 ecx                    ; ECX = ECX - 1
    push                 ecx                    ; put ECX on the stack
    call                recursive_sum          ; recursive call to recursive_sum!
    add                 esp, 4                  ; pop the parameter from the stack
    add                 ebx, eax                ; EBX = EBX + recursive_sum(EBX -1)
    mov                 ecx, ebx                ; ECX = EBX
end:
    mov                 [value], ecx           ; at this point, ECX contains the result
    mov                 [value], ecx           ; save ECX, the return value, in memory
    popa                ; restore registers
    mov                 eax, [value]           ; put the saved returned value into eax
    pop                 ebp                    ; restore EBP
    ret                                     ; return
```

# A Full Example

```
L      dd  42, 43, 44, 45, 56
```

```
...
```

```
push   dword L
```

```
call   func
```

```
add    esp, 4
```

```
call   print_int
```

```
...
```

```
func:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    push   [ebp+8]
```

```
    push   8
```

```
    call   reference
```

```
    add    esp, 8
```

```
    add    eax, 10
```

```
    pop    ebp
```

```
    ret
```

```
reference:
```

```
    push   ebp
```

```
    mov    ebp, esp
```

```
    mov    eax, [ebp+12]
```

```
    add    eax, [ebp+8]
```

```
    mov    eax, [eax]
```

```
    pop    ebp
```

```
    ret
```

ESP →

XXXX



# Conclusion

- You must absolutely make sure you fully understand all code examples in this set of slides
  - Not that this is not true for all code examples in this course ;)
- In the next set of lecture notes we'll talk about local variables in subprograms